



LSI
Logistics
Software
International

**Logistics Solutions Provider
to
Supply Chain Management**



Mobility Solutions
ISV/Software Solutions
Business Process and Integration

Suite 9.2, Level 1
Zenith Business Centre
6 Reliance Drive
Tuggerah NSW 2259
Australia
Tel: +61 2 4351 3500
Email: support@lsi.net.au
Web site: www.lsi.net.au
ABN: 33 414 337 680

iSupply software application - release advice - version 7.29.1.1

Prerequisites - iSupply

iSupply version 7.28.1.1
Microsoft .NET Framework 4.0
Microsoft Report Viewer 2010 SP1
SAP Crystal Reports Runtime Engine for .NET Framework 4

Prerequisites - iSupplyRF

Microsoft .NET Compact Framework 3.5

iSupply release and version details

iSupply version: 7.29.1.1
Release status: General release
Applications released: iSupply, iSupplyWeb, iSupplyRF

This release must be installed to the test environment and user acceptance tested before installation to the live environment

iSupply version 7.29.1.1

released 29/01/2009 (015365)

MSI path and name:

<http://www.lsi.net.au/files/versions/iSupply-7-29-1-1.zip>

SQL update scripts:

DB7-29-1-1.sql

Release inclusions and notes

Job-no	Code	Details/remarks
013557	LS	RF put away - validate expiry date entry3
014590/05	SP	Import pick slips - pick customer orders before bin stock
014590/06	SP	RF put away - show existing bin locations
014590/06	SP	RF put away - show and select customer order data
014590/06	SP	RF Walk-in orders - store cash account code when starting a walk-in order, to be retrieved when sending the completed order to GP
014590/07	SP	Consignment details entry - alert if on-hold or COD
014590/07	SP	Order entry/enquiry - reset on-hold/COD flags
014590/07	SP	Print manifest details - specific delivery run sheet format
014590/07	SP	Build manifests - add consignments to existing manifest
015103	LS	RF Task Monitor - update percentage complete from RF put away
015359	MS	Consignment proof of delivery export
<u>Incorporations from fix versions</u>		
<u>From version 7.24.1.4</u>		
015399	HW	Scan & Pack Orders - rectify SSCC number being generating incorrectly
015402	DH	Consignment details entry/enquiry - reduce time taken dispatching scan pack orders
015404	HW	Consignment details entry/enquiry - rectify TNT label prefix not appearing at the start of the label number
015409	HW	Import orders from Prism - rectify eCS importing the same file twice
015410	CA	Scan & Pack Orders - rectify SSCC number creation when using single unit pack (by unit)
015411	HW	Import orders from SAP - reject files that have a product appearing more than once for one store
015411	HW	Import orders from Oracle - reject files that have a product appearing more than once for one store

New maintainable settings

Setting	Details
Sender Details	Check customer credit

Import/export file format changes

Transaction	Data fields
None	None

Notes

Sender Details Maintenance--->Scanpack settings

New setting "Check credit hold"

Select how an order/pick slip is checked to see if the pick/pack/despatch is to be held pending a despatch decision-

- a) Cash sales
- b) Cash sales and credit hold
- c) Never

System Setup---<Consignment note entry/enquiry settings

New setting "Export delivered c/notes only"

Checked- only consignments that re delivered, ie there is delivery tracking event recorded for the consignment, are exported to the host via "Export consignment note details"

iSupply install steps for this release when upgrading from iSupply version 7.28.1.1

Preparation

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

Application server (x86)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-29-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-29-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-29-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-29-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
 - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client").
 - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
 - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client").
 - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-29-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-29-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Web server (x64)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-29-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-29-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB7-29-1-1.sql.

Finalisation

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.