



**LSI**  
Logistics  
Software  
International

**Logistics Solutions Provider  
to  
Supply Chain Management**



Mobility Solutions  
ISV/Software Solutions  
Business Process and Integration

Suite 9.2, Level 1  
Zenith Business Centre  
6 Reliance Drive  
Tuggerah NSW 2259  
Australia  
Tel: +61 2 4351 3500  
Email: [support@lsi.net.au](mailto:support@lsi.net.au)  
Web site: [www.lsi.net.au](http://www.lsi.net.au)  
ABN: 33 414 337 680

**iSupply software application - release advice - version 7.50.1.1**

**Prerequisites - iSupply**

iSupply version 7.49.1.1  
Microsoft .NET Framework 4.0  
Microsoft Report Viewer 2010 SP1  
SAP Crystal Reports Runtime Engine for .NET Framework 4

**Prerequisites - iSupplyRF**

Microsoft .NET Compact Framework 3.5

**iSupply release and version details**

iSupply version: 7.50.1.1  
Release status: General release  
Applications released: iSupply, iSupplyWeb, iSupplyRF

**This release must be installed to the test environment and user acceptance tested before installation to the live environment**

**iSupply version 7.50.1.1**

**released 04/02/2011 (017272)**

**MSI path and name:**

**<http://www.lsi.net.au/files/versions/iSupply-7-50-1-1.zip>**

**SQL update scripts:**

**DB7-50-1-1.sql**

**Release inclusions and notes**

Job-no	Code	Details/remarks
015231	LS	iSupply wide - correct field names for dangerous goods
016259	LS	iSupplyWeb - Consigning - rectify positioning of state and special instructions
016425	DH	Export consignment data to transporter - Toll Ipec - handle the concatenation of the the alternate transporter code based on the transporter's label number style
016548	LS	iSupplyWeb - Consigning - rectify logic that determines the location of the shipment advice stylesheet
016725	LS	iSupplyWeb - Consigning - reposition location of the head port to be the same as the windows equivalent
016906	LS	iSupplyWeb - rectify reference to the dangerous goods web service
017008	LS	iSupplyWeb - Consigning - consider the service's weight rounding setting
017026	LS	iSupplyWeb - Consigning - expand the display of the prefix field to allow up to 5 characters
017151	VA	iSupplyWeb - print SSCC style, Toll Express and Toll Ipec freight labels
017151	VA	iSupplyWeb - print Toll Express consignment notes
017151	VA	iSupplyWeb - print Toll Ipec specific manifest
017204	DH	Copy current rates into future rates - rectify program crash when the case of the transporter code and destination code are inconsistent
017253	VA	Import sales orders - new generic XML import
017254	VA	Export sales orders - new generic XML export
<b>Incorporations from fix versions</b>		
<b>From version 7.46.2.3</b>		
017300	DH	Services maintenance - rectify search listing to include all transporter/services

**New maintainable settings**

Setting	Details
None	None

**Import/export file format changes**

Transaction	Data fields
None	None

**Notes**

None



## **iSupply install steps for this release when upgrading from iSupply version 7.49.1.1**

### **Preparation**

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

### **Application server (x86)**

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-50-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-50-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

### **Application server (x64)**

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 7-50-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 7-50-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
  - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client").
  - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
  - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client").
  - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

### **Web server (x86)**

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-50-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-50-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

### **Web server (x64)**

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 7-50-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 7-50-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

### **Database server**

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB7-50-1-1.sql.

### **Finalisation**

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.