CUSTOMER SATEFACTOR QUICK RESPONSE DISTRIBUTION JUST IN TIME UST IN TIME ENTERPRISE INTEGRATION	Logistics Software International	Logistics Sol Supply Chair Microsoft GOLD CERTIFIED Partner	utions Provider to n Management Mobility Solutions ISV/Software Solutions Business Process and Integration	Suite 9.2, Level 1 Zenith Business Centre 6 Reliance Drive Tuggerah NSW 2259 Australia Tel: +61 2 4351 3500 Email: <u>support@lsi.net.au</u> Web site: <u>www.lsi.net.au</u> ABN: 33 414 337 680		
iSupply software application - release advice - version 7.41.4.1						
Prerequisites - iSu iSupply version 7.41 Microsoft .NET Frame Microsoft Report View SAP Crystal Reports	pply .3.1 ework 4.0 wer 2010 SP1 Runtime Engine for	Pre Mic .NET Framework 4	erequisites - iSupplyRf rosoft .NET Compact Fra	mework 3.5		
iSupply release an	<u>d version details</u>					
iSupply version:	7.41.4.1	7.41.4.1				
Release status:	General rele	General release				
Applications released	I: iSupply, iSu	iSupply, iSupplyWeb, iSupplyRF				
This release m	ust be installed to	o the test environ	ment and user accepta	ance tested before		
	Insta	allation to the live	environment			

Release inclusions and notes

Code

Job-no

Details/remarks

016448	SB	RF pick/pack -	rectify password of the day calculation		
016470	CL	Consignment details entry/update/enquiry - Print consignments (generic laser) - print multiple pages if a consignment contains more than 4 references			
016505	GM	Export consignment data to transporter - Mainfreight - export packing dimensions			
016536	DH	Manifest build - tidy up organisation of fields in iSupplyWeb			
016539	DH	Import orders - Integrator - rectify handling products within the file that do not exist in iSupply			
016547	LS	iSupplyWeb - UAT fixes			
016550	DH	Export consignment note data - EIS - do not send freight charge as delivery charge if no delivery charge exists			
016556	DH	Export consignment data to transporter - change position within the program where the exported flag is updated			
016568	PC	Consignment details entry - rectify customer manifest reprinting a second copy			
016570	PC	RF pick/pack - update the current bin location on the RF Task Monitor when using the sender/warehouse setting Do not scan bin location			
016571	PC	Import pick slips - Jiwa - ignore pick slip lines that do not have a bin location code			
016572	PC	RF KPI Report - add product variance column to detail section			
016573	PC	Print user id labels - output the user id correctly without carriage returns			
016585	PC	RF pick/pack - remove users access to SSCC field in IBN screen			
016591	SB	System Setup maintenance - rectify saving scales settings			
016602	DH	Consignment details entry - rectify casual receiver consignment save			
016605	DH	Export consignment note data - include todays consignments in export via eCS			
016606	AI	Import track and trace details - Booth Transport - modify import to handle new root element			
016613	YM	Consignment details entry - rectify dangerous goods popup in orders mode			
016621	DH	Export consignment note data - XML Extended - include Charged kilograms field			
		Incorporations from fix versions			
		From version 7.39.1.2			
016385	GT	Trading partner products maintenance - Print mode - rectify load of products with a blank trading partner keycode			
016436	GT	Create AASNs - Generic (ASN734P) - rectify fields in the AASN header that did not output the required data			
		From version 7.41.2.3			
016563	PC	RF KPI Report -	RF KPI Report - Rectify search criteria for date range and task completion type		
<u>New mainta</u>	ainable se	<u>ttings</u>			
Setting			Details		
None			None		
Import/exp	oort file fo	rmat changes			
Transaction			Data fields		
Carrier Export - Mainfreight			Export pack unit dimensions		
Pick Slip Import - Jiwa			Ignore pick slip lines that do not have a bin location		
Freight Tracking Import - Booth Transport			Root node added to format		
Data Warehouse Export - Generic			Include todays consignments in export via eCS		

<u>Notes</u>

None

iSupply install steps for this release when upgrading from iSupply version 7.41.3.1

Preparation

- 1. Ensure all users are logged out of iSupply and cannot log in.
- 2. Stop the eCS service on the server that runs it.
- 3. Stop any external processes that may access the iSupply database.
- 4. Make a backup copy of the iSupply SQL database.

Application server (x86)

- 1. Uninstall the currently installed iSupply Windows version via Control Panel.
- 2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
- 3. Install iSupply Windows 7-41-4-1.msi by running "setup.exe".
- 4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
- 5. Install iSupply eCS Service 7-41-4-1.msi by running "setup.exe".
- 6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service
- \iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

- 1. Uninstall the currently installed iSupply Windows version via Control Panel.
- 2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
- 3. Install iSupply Windows 7-41-4-1 x64.msi by running "setup.exe".

4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.

5. Install iSupply eCS Service 7-41-4-1 x64.msi by running "setup.exe".

6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service

- $\label{eq:service} \ensuremath{\mathsf{viSupplyeCSService.exe.config}}\xspace \ensuremath{\mathsf{has}}\xspace \ensuremath{\mathsf{been}}\xspace \ensuremath{\mathsf{ubc}}\xspace \ensuremath{\mathsf{viSupplyeCSService.exe.config}}\xspace \ensuremath{\mathsf{has}}\xspace \ensuremath{\mathsf{been}}\xspace \ensuremath{\mathsf{ubc}}\xspace \ensuremath{\mathsf{ubc}}\xspace$
- 7. NGEN iSupply Windows
- 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client\").
 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
- 8. NGEN iSupply eCS Service
- 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client\").
- 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

- 1. Uninstall the currently installed iSupply Web Services version via Control Panel.
- 2. Uninstall the currently installed iSupply Web version via Control Panel.
- 3. Install iSupply Web Services 7-41-4-1.msi by running "setup.exe".

4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.

5. Install iSupply Web 7-41-4-1.msi by running "setup.exe".

6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Web server (x64)

- 1. Uninstall the currently installed iSupply Web Services version via Control Panel.
- 2. Uninstall the currently installed iSupply Web version via Control Panel.
- 3. Install iSupply Web Services 7-41-4-1 x64.msi by running "setup.exe".
- 4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
- 5. Install iSupply Web 7-41-4-1 x64.msi by running "setup.exe".

6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB7-41-4-1.sql.

Finalisation

- 1. Test run iSupply.
- 2. Start the eCS service on the server that runs it.
- 3. Start any external processes that may access the iSupply database.
- 4. Allow users to login to iSupply.