



LSI
Logistics
Software
International

Logistics Solutions Provider
to
Supply Chain Management



Mobility Solutions
ISV/Software Solutions
Business Process and Integration

Suite 9.2, Level 1
Zenith Business Centre
6 Reliance Drive
Tuggerah NSW 2259
Australia
Tel: +61 2 4351 3500
Email: support@lsi.net.au
Web site: www.lsi.net.au
ABN: 33 414 337 680

iSupply software application - release advice - version 8.14.1.1

Prerequisites - iSupply

iSupply version 8.13.1.1
Microsoft .NET Framework 4.0
Microsoft Report Viewer 2010 SP1
SAP Crystal Reports Runtime Engine for .NET Framework 4

Prerequisites - iSupplyRF

Microsoft .NET Compact Framework 3.5

iSupply release and version details

iSupply version: 8.14.1.1
Release status: General release
Applications released: iSupply, iSupplyWeb, iSupplyRF

This release must be installed to the test environment and user acceptance tested before installation to the live environment

iSupply version 8.14.1.1 released 03/07/2013 (018442)

MSI path and name: <http://www.lsi.net.au/files/versions/iSupply-8-14-1-1.zip>

SQL update scripts: DB8-14-1-1.sql

Release inclusions and notes

Job-no	Code	Details/remarks
--------	------	-----------------

018380	SC	Consignment Details Entry Enforce packer name according to Sender Details settings iSupply/iSupplyWeb [TD2]
018387	SC	Print Manifest Details Include new sorting options for the delivery runsheet iSupply [TD6]
018412	ST	Freight Label Print/Reprint AaE - rectify printing of special instructions iSupply/iSupplyWeb [TD6] (NHU)
018438	SC	Pick/Pack and Bulk Pick Show order transporter/service when closing pick slip iSupply/iSupplyRF [TD6]
018446	SC	Consignment Details Entry Advise the user if the host system is printing an invoice iSupply [TD2]
018451	SC	Receive Shipment Advices Improve shipment advice search when creating a new receiving task iSupplyRF [TD6] (NHU)
018452	SC	Over The Counter Orders Improve scanning performance iSupplyRF [TD6] (NHU)
018454	SC	Confirm RF Pick/Pack Boxes Show outstanding IBNs for same ship-to as an informational display iSupply [TD6] (NHU)
018459	SC	Pick/Pack Rectify crash with parallel transactions error message iSupplyRF [TD6] (NHU)
018461	LS	Transporter Details Maintenance Improve validation of label number style and printer combination iSupply [TD2] (NHU)
018462	SC	RF Task Monitor Disable User id entry box for receiving tasks iSupply [TD8] (NHU)
018462	SC	RF Task Monitor Disable User id update for receiving tasks iSupply [TD6] (NHU)
018463	SC	Build Manifests Optionally exclude services from the manifest build iSupply/iSupplyWeb [TD2]
018465	SC	Receive Shipment Advice Improve performance iSupplyRF [TD6] (NHU)
018466	SC	Export Despatched Orders Include User id in export XML file iSupply [TD6] (NHU)
		Incorporations from fix versions
		From version 8.7.10.1
018459	SC	Pick/Pack Rectify crash with parallel transactions error message iSupplyRF [TD8] (NHU)

New maintainable settings

Setting	Details
None	None

Import/export file format changes

Transaction	Data fields
None	None

Notes

Sender Details Maintenance

=====

Option CHECK PACKER has been changed to a drop down with three options - check that your required option is selected.

Sender/Warehouse Details Maintenance

=====

New checkbox in More Details--->RF Settings SHOW ORDER TRANSPORTER/SERVICE - set up as required.

Services Maintenance

=====

New checkbox EXCLUDE MANIFESTING - set up as required.

iSupply install steps for this release when upgrading from iSupply version 8.13.1.1

Preparation

1. Ensure all users are logged out of iSupply and cannot log in.
2. Stop the eCS service on the server that runs it.
3. Stop any external processes that may access the iSupply database.
4. Make a backup copy of the iSupply SQL database.

Application server (x86)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 8-14-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 8-14-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

1. Uninstall the currently installed iSupply Windows version via Control Panel.
2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
3. Install iSupply Windows 8-14-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
5. Install iSupply eCS Service 8-14-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service\iSupplyeCSService.exe.config" has been updated with the server and database names.
7. NGEN iSupply Windows
 - 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client").
 - 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
8. NGEN iSupply eCS Service
 - 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client").
 - 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 8-14-1-1.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 8-14-1-1.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Web server (x64)

1. Uninstall the currently installed iSupply Web Services version via Control Panel.
2. Uninstall the currently installed iSupply Web version via Control Panel.
3. Install iSupply Web Services 8-14-1-1 x64.msi by running "setup.exe".
4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
5. Install iSupply Web 8-14-1-1 x64.msi by running "setup.exe".
6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB8-14-1-1.sql.

Finalisation

1. Test run iSupply.
2. Start the eCS service on the server that runs it.
3. Start any external processes that may access the iSupply database.
4. Allow users to login to iSupply.