CUSTOMER SATISFACTION TRAISFORT QUICK RESPONSE DISTRIBUTION JUST IN THRE WAREHOUSING ENTERRISE INTEGRATION	COMMERCE Lo	gistics ftware rnational	Logistics Solutions Provider to Supply Chain Management Microsoft GOLD CERTIFIED Partner Mobility Solutions ISV/Software Solutions Business Process and Integration	Suite 9.2, Level 1 Zenith Business Centre 6 Reliance Drive Tuggerah NSW 2259 Australia Tel: +61 2 4351 3500 Email: <u>support@lsi.net.au</u> Web site: <u>www.lsi.net.au</u> ABN: 33 414 337 680
	iSupply so	oftware ap	plication - release advice - version	9.33.2.1
Prerequisite iSupply versio Microsoft .NET Microsoft Repo SAP Crystal Re	n 9.33.1.1 Framework 4 ort Viewer 201	LO SP1	Prerequisites - iSupplyRF Microsoft .NET Compact Fra .NET Framework 4	
iSupply relea iSupply versio Release status Applications re This rele	n: 5: eleased:	9.33.2.1 General relea iSupply, iSup installed to	ase pplyWeb, iSupplyRF o the test environment and user accepta illation to the live environment	nce tested before
<u>iSupply vers</u> MSI path and SQL update s	d name:	http://	ed 14/05/2019 (021198) /www.lsi.net.au/files/versions/iSupply 3-2-1.sql	7-9-33-2-1.zip
Release inc	lusions and	l notes		
Job-no	Code	Details/remarks		
021199	CA	Consignment Entry Rectify display of cubic details in Enquire and Change modes iSupply		
021199			play of cubic details in Enquire and change	modes
New mainta	ainable sett	iSuppĺy		modes
	ainable sett	iSuppĺy	Details	modes
New mainta	ainable sett	iSuppĺy		modes
New mainta		iSupply	Details None	modes
New mainta Setting None		iSupply	Details None	modes

None

iSupply install steps for this release when upgrading from iSupply version 9.33.1.1

Preparation

- 1. Ensure all users are logged out of iSupply and cannot log in.
- 2. Stop the eCS service on the server that runs it.
- 3. Stop any external processes that may access the iSupply database.
- 4. Make a backup copy of the iSupply SQL database.

Application server (x86)

- 1. Uninstall the currently installed iSupply Windows version via Control Panel.
- 2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
- 3. Install iSupply Windows 9-33-2-1.msi by running "setup.exe".
- 4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.
- 5. Install iSupply eCS Service 9-33-2-1.msi by running "setup.exe".
- 6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service
- \iSupplyeCSService.exe.config" has been updated with the server and database names.

Application server (x64)

- 1. Uninstall the currently installed iSupply Windows version via Control Panel.
- 2. Uninstall the currently installed iSupply eCS Service version via Control Panel.
- 3. Install iSupply Windows 9-33-2-1 x64.msi by running "setup.exe".

4. Ensure that the configuration file "C:\Program Files\LSI\iSupply Windows\iSupplyWindows.exe.config" has been updated with the server and database names.

- 5. Install iSupply eCS Service 9-33-2-1 x64.msi by running "setup.exe".
- 6. Ensure that the configuration file "C:\Program Files\LSI\iSupply eCS Service
- $\label{eq:service} \ensuremath{\mathsf{viSupplyeCSService.exe.config}}\xspace \ensuremath{\mathsf{has}}\xspace \ensuremath{\mathsf{been}}\xspace \ensuremath{\mathsf{viSupplyeCSService.exe.config}}\xspace \ensuremath{\mathsf{has}}\xspace \ensuremath{\mathsf{been}}\xspace \ensuremath{\mathsf{has}}\xspace \ensuremath{\mathsf{been}}\xspace \ensuremath{\mathsf{has}}\xspace \ensuremath{\mathsf{beensuremath{\mathsf{viSupplyeCSService.exe.config}}\xspace \ensuremath{\mathsf{has}}\xspace \ensuremath{\mathsf{beensuremath{\mathsf{bee}}}\xspace \ensuremath{\mathsf{has}}\xspace \ensuremath{\mathsf{beensuremath{\mathsf{bee}}}\xspace \ensuremath{\mathsf{beensuremath{beensuremath{\mathsf{beensuremath{\mathsf{beensuremath{\mathsf{beensuremath{\mathsf{beensuremath{\mathsf{beensuremath{beensuremath{beensuremath{beensuremath{beensuremath{beensuremath{be$
- 7. NGEN iSupply Windows
- 7.1. Place the files "ngen.exe" and "NGENiSupplyWindows.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply Windows\Client\").
 7.2. Run the NGENiSupplyWindows.bat from command prompt as an Administrator
- 8. NGEN iSupply eCS Service
- 8.1. Place the files "ngen.exe" and "NGENiSupplyeCSService.bat" into iSupply's installation directory (Default: "C:\Program Files\LSI\iSupply eCS Service\Client\").
- 8.2. Run the "NGENiSupplyeCSService.bat" from command prompt as an Administrator

Web server (x86)

- 1. Uninstall the currently installed iSupply Web Services version via Control Panel.
- 2. Uninstall the currently installed iSupply Web version via Control Panel.
- 3. Install iSupply Web Services 9-33-2-1.msi by running "setup.exe".
- 4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
- 5. Install iSupply Web 9-33-2-1.msi by running "setup.exe".
- 6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Web server (x64)

- 1. Uninstall the currently installed iSupply Web Services version via Control Panel.
- 2. Uninstall the currently installed iSupply Web version via Control Panel.
- 3. Install iSupply Web Services 9-33-2-1 x64.msi by running "setup.exe".
- 4. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWebServices\Web.config" has been updated with the server and database names.
- 5. Install iSupply Web 9-33-2-1 x64.msi by running "setup.exe".
- 6. Ensure that the configuration file "C:\inetpub\wwwroot\iSupplyWeb\Web.config" has been updated with the URL of the iSupplyWebServices.

Database server

1. Run the following database update script(s) (using SQL Server Management Studio) to update the iSupply database: DB9-33-2-1.sql.

Finalisation

- 1. Test run iSupply.
- 2. Start the eCS service on the server that runs it.
- 3. Start any external processes that may access the iSupply database.
- 4. Allow users to login to iSupply.